

# Setting up ActiveMQ for Fineract 1.0

Note: Run ActiveMQ before the fineract server.

## Installing ActiveMQ

### Prerequisites:

- Atleast java Runtime Environment (JRE) JRE 1.7 (1.6 for version <=5.10.0)
- The JAVA\_HOME environment variable must be set to the directory where the JRE is installed

## Installation procedure for Ubuntu (preferably ubuntu 14.04)

1. Download the ActiveMQ zipped tarball file to the Unix machine  
wget -c "<http://www.apache.org/dyn/closer.cgi?filename=/activemq/5.15.1/apache-activemq-5.15.1-bin.tar.gz&action=download>" -O [activemq\_install\_dir]
2. Extract the files from the zipped tarball into a directory of your choice.  
cd [activemq\_install\_dir]  
tar zxvf activemq-x.x.x-bin.tar.gz

## Managing ActiveMQ

### Starting ActiveMQ

1. Change to the installation directory and run ActiveMQ  
cd [activemq\_install\_dir]\bin  
./activemq start

### Stopping ActiveMQ

1. Change to the installation directory and stop ActiveMQ  
cd [activemq\_install\_dir]\bin  
./activemq stop

## Check the status of ActiveMQ

1. ./activemq status

## Installation procedure for Windows

1. Download the latest stable release (see [Download](#) -> "The latest stable release")
2. Extract ActiveMQ from the ZIP file into a directory of your choice

## Managing ActiveMQ

### Starting ActiveMQ

1. Change to the installation directory and run ActiveMQ  
cd [activemq\_install\_dir]\bin  
./activemq start

### Stopping ActiveM

1. Change to the installation directory and stop ActiveMQ  
cd [activemq\_install\_dir]\bin  
./activemq stop

## Recently Faced Errors

**-su: 3: cannot create /root/apache-activemq-5.15.1//data/activemq.pid: Permission denied**

1. Open the file [activemq installation directory]/bin/[linux-x86-32/linux-x86-64]/activemq
2. Uncomment the line RUN\_AS\_USER.
3. Edit like RUN\_AS\_USER =Your username.
4. Save it and exit.
5. Go back to [activemq installation directory]/bin/ and start the activemq.