

1.1.4.2.2.

1.1.4.2.1. DB2

1.1.4.2.

1.1.4.2.3. JBoss 4

Using the Geronimo database pool wizard 4

Database Pools [view]

Create Database Pool -- Step 1: Select Name and Database

Name of Database Pool:

Derby_Test

A name that is different than the name for any other database pools in the server (no spaces in the name please).

Database Type:

Derby embedded

The type of database the pool will connect to.

Next

[Cancel](#)

JDBCJDBCJAR test 1.5.

Database Pools [view]

Create Database Pool -- Step 2: Select Driver, JAR, Parameters

JDBC Driver Class:

org.apache.derby.jdbc.EmbeddedDr

See the documentation for your JDBC driver.

Driver JAR:

org.apache.cxf/cxf-rt-bindings-xml/2.0-incubator-RC-20070213210000/jar
org.apache.cxf/cxf-rt-core/2.0-incubator-RC-20070213210000/jar
org.apache.cxf/cxf-rt-databinding-jaxb/2.0-incubator-RC-20070213210000/jar
org.apache.cxf/cxf-rt-frontent-jaxws/2.0-incubator-RC-20070213210000/jar
org.apache.cxf/cxf-rt-frontent-simple/2.0-incubator-RC-20070213210000/jar
org.apache.cxf/cxf-rt-transport-http/2.0-incubator-RC-20070213210000/jar
org.apache.cxf/cxf-tools-common/2.0-incubator-RC-20070213210000/jar
org.apache.derby/derby/10.2.2.0/jar
org.apache.derby/derbyclient/10.2.2.0/jar
org.apache.derby/derbynet/10.2.2.0/jar

The JAR(s) required to make a connection to the database. Use CTRL-click or SHIFT-click to select multiple jars.
The JAR(s) should already be installed under Geronimo/repository/ (or [Download a Driver](#))

DB User Name:

The username used to connect to the database

DB Password:

Confirm Password:

The password used to connect to the database

Driver Connection Properties

Typical JDBC URL:

jdbc:derby:{Database}

Database:

test

A property used to connect to Derby embedded. May be optional (see JDBC driver documentation).

Next

[Cancel](#)

Test Connection

Database Pools		[view]
Create Database Pool -- Step 3: Final Pool Configuration		
JDBC Connect URL:	jdbc:derby:test Make sure the generated URL fits the syntax for your JDBC driver.	
Driver Status:	Loaded Successfully	
Connection Pool Parameters		
Pool Min Size:	 The minimum number of connections in the pool. Leave blank for default.	
Pool Max Size:	 The maximum number of connections in the pool. Leave blank for default.	
Blocking Timeout:	(in milliseconds) The length of time a caller will wait for a connection. Leave blank for default.	
Idle Timeout:	(in minutes) How long a connection can be idle before being closed. Leave blank for default.	
Test Connection Skip Test and Deploy Skip Test and Show Plan		
Cancel		

Deploy Show Plan DB 1.1.4.2.1. DB2

Database Pools		[view]
Create Database Pool -- Step 4: Test Connection		
Test Result:	Connected to Apache Derby 10.2.2.0 - (485682)	
Deploy Show Plan		
Cancel		